

1157	One of the library files needed to run this application cannot be found.	ERROR_DLL_NOT_FOUND
1158	The current process has used all of its system allowance of handles for Window Manager objects.	ERROR_NO_MORE_USER_HANDLES
1159	The message can be used only with synchronous operations.	ERROR_MESSAGE_SYNC_ONLY
1160	The indicated source element has no media.	ERROR_SOURCE_ELEMENT_EMPTY
1161	The indicated destination element already contains media.	ERROR_DESTINATION_ELEMENT_FULL
1162	The indicated element does not exist.	ERROR_ILLEGAL_ELEMENT_ADDRESS
1163	The indicated element is part of a magazine that is not present.	ERROR_MAGAZINE_NOT_PRESENT
1164	The indicated device requires reinitialization due to hardware errors.	ERROR_DEVICE_REINITIALIZATION_NEEDED
1165	The device has indicated that cleaning is required before further operations are attempted.	ERROR_DEVICE_REQUIRES_CLEANING
1166	The device has indicated that its door is open.	ERROR_DEVICE_DOOR_OPEN
1167	The device is not connected.	ERROR_DEVICE_NOT_CONNECTED
1168	Element not found.	ERROR_NOT_FOUND
1169	There was no match for the specified key in the index.	ERROR_NO_MATCH
1170	The property set specified does not exist on the object.	ERROR_SET_NOT_FOUND
1171	The point passed to GetMouseMovePointsEx is not in the buffer.	ERROR_POINT_NOT_FOUND
1172	The tracking (workstation) service is not running.	ERROR_NO_TRACKING_SERVICE
1173	The Volume ID could not be found.	ERROR_NO_VOLUME_ID
1174	The specified Very Large Memory (64-bit) operation is invalid.	ERROR_INVALID_VLM_OPERATION
1175	Unable to remove the file to be replaced.	ERROR_UNABLE_TO_REMOVE_REPLACED
1176	Unable to move the replacement file to the file to be replaced. The file to be replaced has retained its original name.	ERROR_UNABLE_TO_MOVE_REPLACEMENT
1177	Unable to move the replacement file to the file to be replaced. The file to be replaced has been renamed using the backup name.	ERROR_UNABLE_TO_MOVE_REPLACEMENT_2
1178	The volume change journal is being deleted.	ERROR_JOURNAL_DELETE_IN_PROGRESS
1179	The volume change journal service is not active.	ERROR_JOURNAL_NOT_ACTIVE
1180	A file was found, but it may not be the correct file.	ERROR_POTENTIAL_FILE_FOUND
1181	The journal entry has been deleted from the journal.	ERROR_JOURNAL_ENTRY_DELETED
1200	The specified device name is invalid.	ERROR_BAD_DEVICE
1201	The device is not currently connected but it is a remembered connection.	ERROR_CONNECTION_UNAVAIL
1202	An attempt was made to remember a device that had previously been remembered.	ERROR_DEVICE_ALREADY_REMEMBERED
1203	No network provider accepted the given network path.	ERROR_NO_NET_OR_BAD_PATH
1204	The specified network provider name is invalid.	ERROR_BAD_PROVIDER
1205	Unable to open the network connection profile.	ERROR_CANNOT_OPEN_PROFILE
1206	The network connection profile is corrupted.	ERROR_BAD_PROFILE
1207	Cannot enumerate a noncontainer.	ERROR_NOT_CONTAINER

1208	An extended error has occurred.	ERROR_EXTENDED_ERROR
1209	The format of the specified group name is invalid.	ERROR_INVALID_GROUPNAME
1210	The format of the specified computer name is invalid.	ERROR_INVALID_COMPUTERNAME
1211	The format of the specified event name is invalid.	ERROR_INVALID_EVENTNAME
1212	The format of the specified domain name is invalid.	ERROR_INVALID_DOMAINNAME
1213	The format of the specified service name is invalid.	ERROR_INVALID_SERVICENAME
1214	The format of the specified network name is invalid.	ERROR_INVALID_NETNAME
1215	The format of the specified share name is invalid.	ERROR_INVALID_SHARENAME
1216	The format of the specified password is invalid.	ERROR_INVALID_PASSWORDNAME
1217	The format of the specified message name is invalid.	ERROR_INVALID_MESSAGE_NAME
1218	The format of the specified message destination is invalid.	ERROR_INVALID_MESSAGEDEST
1219	The credentials supplied conflict with an existing set of credentials.	ERROR_SESSION_CREDENTIAL_CONFLICT
1220	An attempt was made to establish a session to a network server, but there are already too many sessions established to that server.	ERROR_REMOTE_SESSION_LIMIT_EXCEEDED
1221	The workgroup or domain name is already in use by another computer on the network.	ERROR_DUP_DOMAINNAME
1222	The network is not present or not started.	ERROR_NO_NETWORK
1223	The operation was canceled by the user.	ERROR_CANCELLED
1224	The requested operation cannot be performed on a file with a user-mapped section open.	ERROR_USER_MAPPED_FILE
1225	The remote system refused the network connection.	ERROR_CONNECTION_REFUSED
1226	The network connection was gracefully closed.	ERROR_GRACEFUL_DISCONNECT
1227	The network transport endpoint already has an address associated with it.	ERROR_ADDRESS_ALREADY_ASSOCIATED
1228	An address has not yet been associated with the network endpoint.	ERROR_ADDRESS_NOT_ASSOCIATED
1229	An operation was attempted on a nonexistent network connection.	ERROR_CONNECTION_INVALID
1230	An invalid operation was attempted on an active network connection.	ERROR_CONNECTION_ACTIVE
1231	The remote network is not reachable by the transport.	ERROR_NETWORK_UNREACHABLE
1232	The remote system is not reachable by the transport.	ERROR_HOST_UNREACHABLE
1233	The remote system does not support the transport protocol.	ERROR_PROTOCOL_UNREACHABLE
1234	No service is operating at the destination network endpoint on the remote system.	ERROR_PORT_UNREACHABLE
1235	The request was aborted.	ERROR_REQUEST_ABORTED
1236	The network connection was aborted by the local system.	ERROR_CONNECTION_ABORTED
1237	The operation could not be completed. A retry should be performed.	ERROR_RETRY
1238	A connection to the server could not be made because the limit on the number of concurrent connections for this account has been reached.	ERROR_CONNECTION_COUNT_LIMIT
1239	Attempting to log in during an unauthorized time of day for this account.	ERROR_LOGIN_TIME_RESTRICTION
1240	The account is not authorized to log in from this station.	ERROR_LOGIN_WKSTA_RESTRICTION
1241	The network address could not be used for the operation requested.	ERROR_INCORRECT_ADDRESS

1242	The service is already registered.	ERROR_ALREADY_REGISTERED
1243	The specified service does not exist.	ERROR_SERVICE_NOT_FOUND
1244	The operation being requested was not performed because the user has not been authenticated.	ERROR_NOT_AUTHENTICATED
1245	The operation being requested was not performed because the user has not logged on to the network. The specified service does not exist.	ERROR_NOT_LOGGED_ON
1246	Continue with work in progress.	ERROR_CONTINUE
1247	An attempt was made to perform an initialization operation when initialization has already been completed.	ERROR_ALREADY_INITIALIZED
1248	No more local devices.	ERROR_NO_MORE_DEVICES
1249	The specified site does not exist.	ERROR_NO_SUCH_SITE
1250	A domain controller with the specified name already exists.	ERROR_DOMAIN_CONTROLLER_EXISTS
1251	This operation is supported only when you are connected to the server.	ERROR_ONLY_IF_CONNECTED
1252	The group policy framework should call the extension even if there are no changes.	ERROR_OVERRIDE_NOCHANGES
1300	Not all privileges referenced are assigned to the caller.	ERROR_NOT_ALL_ASSIGNED
1301	Some mapping between account names and security IDs was not done.	ERROR_SOME_NOT_MAPPED
1302	No system quota limits are specifically set for this account.	ERROR_NO_QUOTAS_FOR_ACCOUNT
1303	No encryption key is available. A well-known encryption key was returned.	ERROR_LOCAL_USER_SESSION_KEY
1304	The password is too complex to be converted to a LAN Manager password. The LAN Manager password returned is a NULL string.	ERROR_NULL_LM_PASSWORD
1305	The revision level is unknown.	ERROR_UNKNOWN_REVISION
1306	Indicates two revision levels are incompatible.	ERROR_REVISION_MISMATCH
1307	This security ID may not be assigned as the owner of this object.	ERROR_INVALID_OWNER
1308	This security ID may not be assigned as the primary group of an object.	ERROR_INVALID_PRIMARY_GROUP
1309	An attempt has been made to operate on an impersonation token by a thread that is not currently impersonating a client.	ERROR_NO_IMPERSONATION_TOKEN
1310	The group may not be disabled.	ERROR_CANT_DISABLE_MANDATORY
1311	There are currently no logon servers available to service the logon request.	ERROR_NO_LOGON_SERVERS
1312	A specified logon session does not exist. It may already have been terminated.	ERROR_NO_SUCH_LOGON_SESSION
1313	A specified privilege does not exist.	ERROR_NO_SUCH_PRIVILEGE
1314	A required privilege is not held by the client.	ERROR_PRIVILEGE_NOT_HELD
1315	The name provided is not a properly formed account name.	ERROR_INVALID_ACCOUNT_NAME
1316	The specified user already exists.	ERROR_USER_EXISTS
1317	The specified user does not exist.	ERROR_NO_SUCH_USER
1318	The specified group already exists.	ERROR_GROUP_EXISTS
1319	The specified group does not exist.	ERROR_NO_SUCH_GROUP

1320	Either the specified user account is already a member of the specified group, or the specified group cannot be deleted because it contains a member.	ERROR_MEMBER_IN_GROUP
1321	The specified user account is not a member of the specified group account.	ERROR_MEMBER_NOT_IN_GROUP
1322	The last remaining administration account cannot be disabled or deleted.	ERROR_LAST_ADMIN
1323	Unable to update the password. The value provided as the current password is incorrect.	ERROR_WRONG_PASSWORD
1324	Unable to update the password. The value provided for the new password contains values that are not allowed in passwords.	ERROR_ILL_FORMED_PASSWORD
1325	Unable to update the password. The value provided for the new password does not meet the length, complexity, or history requirement of the domain.	ERROR_PASSWORD_RESTRICTION
1326	Logon failure: unknown user name or bad password.	ERROR_LOGON_FAILURE
1327	Logon failure: user account restriction.	ERROR_ACCOUNT_RESTRICTION
1328	Logon failure: account logon time restriction violation.	ERROR_INVALID_LOGON_HOURS
1329	Logon failure: user not allowed to log on to this computer.	ERROR_INVALID_WORKSTATION
1330	Logon failure: the specified account password has expired.	ERROR_PASSWORD_EXPIRED
1331	Logon failure: account currently disabled.	ERROR_ACCOUNT_DISABLED
1332	No mapping between account names and security IDs was done.	ERROR_NONE_MAPPED
1333	Too many local user identifiers (LUIDs) were requested at one time.	ERROR_TOO_MANY_LUIDS_REQUESTED
1334	No more local user identifiers (LUIDs) are available.	ERROR_LUIDS_EXHAUSTED
1335	The subauthority part of a security ID is invalid for this particular use.	ERROR_INVALID_SUB_AUTHORITY
1336	The access control list (ACL) structure is invalid.	ERROR_INVALID_ACL
1337	The security ID structure is invalid.	ERROR_INVALID_SID
1338	The security descriptor structure is invalid.	ERROR_INVALID_SECURITY_DESCR
1340	The inherited access control list (ACL) or access control entry (ACE) could not be built.	ERROR_BAD_INHERITANCE_ACL
1341	The server is currently disabled.	ERROR_SERVER_DISABLED
1342	The server is currently enabled.	ERROR_SERVER_NOT_DISABLED
1343	The value provided was an invalid value for an identifier authority.	ERROR_INVALID_ID_AUTHORITY
1344	No more memory is available for security information updates.	ERROR_ALLOTTED_SPACE_EXCEEDED
1345	The specified attributes are invalid, or incompatible with the attributes for the group as a whole.	ERROR_INVALID_GROUP_ATTRIBUTES
1346	Either a required impersonation level was not provided, or the provided impersonation level is invalid.	ERROR_BAD_IMPERSONATION_LEVEL
1347	Cannot open an anonymous level security token.	ERROR_CANT_OPEN_ANONYMOUS
1348	The validation information class requested was invalid.	ERROR_BAD_VALIDATION_CLASS
1349	The type of the token is inappropriate for its attempted use.	ERROR_BAD_TOKEN_TYPE
1350	Unable to perform a security operation on an object that has no associated security.	ERROR_NO_SECURITY_ON_OBJECT
1351	Configuration information could not be read from the domain controller, either because the	ERROR_CANT_ACCESS_DOMAIN_INFO

	machine is unavailable, or access has been denied.	
1352	The security account manager (SAM) or local security authority (LSA) server was in the wrong state to perform the security operation.	ERROR_INVALID_SERVER_STATE
1353	The domain was in the wrong state to perform the security operation.	ERROR_INVALID_DOMAIN_STATE
1354	This operation is only allowed for the Primary Domain Controller of the domain.	ERROR_INVALID_DOMAIN_ROLE
1355	The specified domain did not exist.	ERROR_NO_SUCH_DOMAIN
1356	The specified domain already exists.	ERROR_DOMAIN_EXISTS
1357	An attempt was made to exceed the limit on the number of domains per server.	ERROR_DOMAIN_LIMIT_EXCEEDED
1083	The executable program that this service is configured to run in does not implement the service.	ERROR_SERVICE_NOT_IN_EXE
1100	The physical end of the tape has been reached.	ERROR_END_OF_MEDIA
1101	A tape access reached a filemark.	ERROR_FILEMARK_DETECTED
1102	The beginning of the tape or a partition was encountered.	ERROR_BEGINNING_OF_MEDIA
1103	A tape access reached the end of a set of files.	ERROR_SETMARK_DETECTED
1104	No more data is on the tape.	ERROR_NO_DATA_DETECTED
1105	Tape could not be partitioned.	ERROR_PARTITION_FAILURE
1106	When accessing a new tape of a multivolume partition, the current block size is incorrect.	ERROR_INVALID_BLOCK_LENGTH
1107	Tape partition information could not be found when loading a tape.	ERROR_DEVICE_NOT_PARTITIONED
1108	Unable to lock the media eject mechanism.	ERROR_UNABLE_TO_LOCK_MEDIA
1109	Unable to unload the media.	ERROR_UNABLE_TO_UNLOAD_MEDIA
1110	The media in the drive may have changed.	ERROR_MEDIA_CHANGED
1111	The I/O bus was reset.	ERROR_BUS_RESET
1112	No media in drive.	ERROR_NO_MEDIA_IN_DRIVE
1113	No mapping for the Unicode character exists in the target multi-byte code page.	ERROR_NO_UNICODE_TRANSLATION
1114	A dynamic link library (DLL) initialization routine failed.	ERROR_DLL_INIT_FAILED
1115	A system shutdown is in progress.	ERROR_SHUTDOWN_IN_PROGRESS
1116	Unable to abort the system shutdown because no shutdown was in progress.	ERROR_NO_SHUTDOWN_IN_PROGRESS
1117	The request could not be performed because of an I/O device error.	ERROR_IO_DEVICE
1118	No serial device was successfully initialized. The serial driver will unload.	ERROR_SERIAL_NO_DEVICE
1119	Unable to open a device that was sharing an interrupt request (IRQ) with other devices. At least one other device that uses that IRQ was already opened.	ERROR_IRQ_BUSY
1120	A serial I/O operation was completed by another write to the serial port. (The IOCTL_SERIAL_XOFF_COUNTER reached zero.)	ERROR_MORE_WRITES
1121	A serial I/O operation completed because the timeout period expired. (The IOCTL_SERIAL_XOFF_COUNTER did not reach zero.)	ERROR_COUNTER_TIMEOUT
1122	No ID address mark was found on the floppy disk.	ERROR_FLOPPY_ID_MARK_NOT_FOUND

1123	Mismatch between the floppy disk sector ID field and the floppy disk controller track address.	ERROR_FLOPPY_WRONG_CYLINDER
1124	The floppy disk controller reported an error that is not recognized by the floppy disk driver.	ERROR_FLOPPY_UNKNOWN_ERROR
1125	The floppy disk controller returned inconsistent results in its registers.	ERROR_FLOPPY_BAD_REGISTERS
1126	While accessing the hard disk, a recalibrate operation failed, even after retries.	ERROR_DISK_RECALIBRATE_FAILED
1127	While accessing the hard disk, a disk operation failed even after retries.	ERROR_DISK_OPERATION_FAILED
1128	While accessing the hard disk, a disk controller reset was needed, but even that failed.	ERROR_DISK_RESET_FAILED
1129	Physical end of tape encountered.	ERROR_EOM_OVERFLOW
1130	Not enough server storage is available to process this command.	ERROR_NOT_ENOUGH_SERVER_MEMORY
1131	A potential deadlock condition has been detected.	ERROR_POSSIBLE_DEADLOCK
1132	The base address or the file offset specified does not have the proper alignment.	ERROR_MAPPED_ALIGNMENT
1140	An attempt to change the system power state was vetoed by another application or driver.	ERROR_SET_POWER_STATE_VETOED
1141	The system BIOS failed an attempt to change the system power state.	ERROR_SET_POWER_STATE_FAILED
1142	An attempt was made to create more links on a file than the file system supports.	ERROR_TOO_MANY_LINKS
1150	The specified program requires a newer version of Windows.	ERROR_OLD_WIN_VERSION
1151	The specified program is not a Windows or MS-DOS program.	ERROR_APP_WRONG_OS
1152	Cannot start more than one instance of the specified program.	ERROR_SINGLE_INSTANCE_APP
1153	The specified program was written for an earlier version of Windows.	ERROR_RMODE_APP
1154	One of the library files needed to run this application is damaged.	ERROR_INVALID_DLL
1155	No application is associated with the specified file for this operation.	ERROR_NO_ASSOCIATION
1156	An error occurred in sending the command to the application.	ERROR_DDE_FAIL
1157	One of the library files needed to run this application cannot be found.	ERROR_DLL_NOT_FOUND
1158	The current process has used all of its system allowance of handles for Window Manager objects.	ERROR_NO_MORE_USER_HANDLES
1159	The message can be used only with synchronous operations.	ERROR_MESSAGE_SYNC_ONLY
1160	The indicated source element has no media.	ERROR_SOURCE_ELEMENT_EMPTY
1161	The indicated destination element already contains media.	ERROR_DESTINATION_ELEMENT_FULL
1162	The indicated element does not exist.	ERROR_ILLEGAL_ELEMENT_ADDRESS
1163	The indicated element is part of a magazine that is not present.	ERROR_MAGAZINE_NOT_PRESENT
1164	The indicated device requires reinitialization due to hardware errors.	ERROR_DEVICE_REINITIALIZATION_NEEDED
1165	The device has indicated that cleaning is required before further operations are attempted.	ERROR_DEVICE_REQUIRES_CLEANING
1166	The device has indicated that its door is open.	ERROR_DEVICE_DOOR_OPEN
1167	The device is not connected.	ERROR_DEVICE_NOT_CONNECTED
1168	Element not found.	ERROR_NOT_FOUND
1169	There was no match for the specified key in the index.	ERROR_NO_MATCH
1170	The property set specified does not exist on the object.	ERROR_SET_NOT_FOUND
1171	The point passed to GetMouseMovePointsEx is not in the buffer.	ERROR_POINT_NOT_FOUND

1172	The tracking (workstation) service is not running.	ERROR_NO_TRACKING_SERVICE
1173	The Volume ID could not be found.	ERROR_NO_VOLUME_ID
1174	The specified Very Large Memory (64-bit) operation is invalid.	ERROR_INVALID_VLM_OPERATION
1175	Unable to remove the file to be replaced.	ERROR_UNABLE_TO_REMOVE_REPLACED
1176	Unable to move the replacement file to the file to be replaced. The file to be replaced has retained its original name.	ERROR_UNABLE_TO_MOVE_REPLACEMENT
1177	Unable to move the replacement file to the file to be replaced. The file to be replaced has been renamed using the backup name.	ERROR_UNABLE_TO_MOVE_REPLACEMENT_2
1178	The volume change journal is being deleted.	ERROR_JOURNAL_DELETE_IN_PROGRESS
1179	The volume change journal service is not active.	ERROR_JOURNAL_NOT_ACTIVE
1180	A file was found, but it may not be the correct file.	ERROR_POTENTIAL_FILE_FOUND
1181	The journal entry has been deleted from the journal.	ERROR_JOURNAL_ENTRY_DELETED
1200	The specified device name is invalid.	ERROR_BAD_DEVICE
1201	The device is not currently connected but it is a remembered connection.	ERROR_CONNECTION_UNAVAIL
1202	An attempt was made to remember a device that had previously been remembered.	ERROR_DEVICE_ALREADY_REMEMBERED
1203	No network provider accepted the given network path.	ERROR_NO_NET_OR_BAD_PATH
1204	The specified network provider name is invalid.	ERROR_BAD_PROVIDER
1205	Unable to open the network connection profile.	ERROR_CANNOT_OPEN_PROFILE
1206	The network connection profile is corrupted.	ERROR_BAD_PROFILE
1207	Cannot enumerate a noncontainer.	ERROR_NOT_CONTAINER
1208	An extended error has occurred.	ERROR_EXTENDED_ERROR
1209	The format of the specified group name is invalid.	ERROR_INVALID_GROUPNAME
1210	The format of the specified computer name is invalid.	ERROR_INVALID_COMPUTERNAME
1211	The format of the specified event name is invalid.	ERROR_INVALID_EVENTNAME
1212	The format of the specified domain name is invalid.	ERROR_INVALID_DOMAINNAME
1213	The format of the specified service name is invalid.	ERROR_INVALID_SERVICENAME
1214	The format of the specified network name is invalid.	ERROR_INVALID_NETNAME
1215	The format of the specified share name is invalid.	ERROR_INVALID_SHARENAME
1216	The format of the specified password is invalid.	ERROR_INVALID_PASSWORDNAME
1217	The format of the specified message name is invalid.	ERROR_INVALID_MESSAGE_NAME
1218	The format of the specified message destination is invalid.	ERROR_INVALID_MESSAGEDEST
1219	The credentials supplied conflict with an existing set of credentials.	ERROR_SESSION_CREDENTIAL_CONFLICT
1220	An attempt was made to establish a session to a network server, but there are already too many sessions established to that server.	ERROR_REMOTE_SESSION_LIMIT_EXCEEDED
1221	The workgroup or domain name is already in use by another computer on the network.	ERROR_DUP_DOMAINNAME
1222	The network is not present or not started.	ERROR_NO_NETWORK

1223	The operation was canceled by the user.	ERROR_CANCELLED
1224	The requested operation cannot be performed on a file with a user-mapped section open.	ERROR_USER_MAPPED_FILE
1225	The remote system refused the network connection.	ERROR_CONNECTION_REFUSED
1226	The network connection was gracefully closed.	ERROR_GRACEFUL_DISCONNECT
1227	The network transport endpoint already has an address associated with it.	ERROR_ADDRESS_ALREADY_ASSOCIATED
1228	An address has not yet been associated with the network endpoint.	ERROR_ADDRESS_NOT_ASSOCIATED
1229	An operation was attempted on a nonexistent network connection.	ERROR_CONNECTION_INVALID
1230	An invalid operation was attempted on an active network connection.	ERROR_CONNECTION_ACTIVE
1231	The remote network is not reachable by the transport.	ERROR_NETWORK_UNREACHABLE
1232	The remote system is not reachable by the transport.	ERROR_HOST_UNREACHABLE
1233	The remote system does not support the transport protocol.	ERROR_PROTOCOL_UNREACHABLE
1234	No service is operating at the destination network endpoint on the remote system.	ERROR_PORT_UNREACHABLE
1235	The request was aborted.	ERROR_REQUEST_ABORTED
1236	The network connection was aborted by the local system.	ERROR_CONNECTION_ABORTED
1237	The operation could not be completed. A retry should be performed.	ERROR_RETRY
1238	A connection to the server could not be made because the limit on the number of concurrent connections for this account has been reached.	ERROR_CONNECTION_COUNT_LIMIT
1239	Attempting to log in during an unauthorized time of day for this account.	ERROR_LOGIN_TIME_RESTRICTION
1240	The account is not authorized to log in from this station.	ERROR_LOGIN_WKSTA_RESTRICTION
1241	The network address could not be used for the operation requested.	ERROR_INCORRECT_ADDRESS
1242	The service is already registered.	ERROR_ALREADY_REGISTERED
1243	The specified service does not exist.	ERROR_SERVICE_NOT_FOUND
1244	The operation being requested was not performed because the user has not been authenticated.	ERROR_NOT_AUTHENTICATED
1245	The operation being requested was not performed because the user has not logged on to the network. The specified service does not exist.	ERROR_NOT_LOGGED_ON
1246	Continue with work in progress.	ERROR_CONTINUE